

ARC[®] GENESIS

電腦版軟體使用簡易步驟



下載ARC軟體

- <https://www.anthemarc.com/downloads/index.php>

anthemarc.com/downloads/index.php

OVERVIEW ARC GENESIS ARC MOBILE ADVANCED TOPICS DOWNLOADS

ARC Genesis
NEW

Download for
Mac OS X
v1.2.3

Download for
Windows (32-bit)
v1.2.3

Download for
Windows (64-bit)
v1.2.3

ARC Mobile

Download for
iOS


Download for
Android

System Requirements: ARC Mobile requires an iOS or Android device and an ARC or PBK compatible audio product. Android phones require a USB OTG adapter to use the optional calibrated microphone. Many Android phones come with these adapters.

選擇需要的版本下載
並安裝於電腦

確認ARC版本

- 如電腦已有安裝ARC，請確認是否為此版本或更新版本



前置準備作業

- 將Antehem擴大機(或其他相容ARC的機器)，連上與電腦相同的網路
- 將內附的校正麥克風用**USB**線連接到電腦上
- 打開**ARC Genesis**程式開始準備校正程序

ARC 測量

- 在程式左上角按下“Launch”後，選擇要校正的擴大機，依照畫面指示依序完成測量步驟
- 系統預設會測量五次(五個點)，分別是最佳聆聽位置+周圍60~90cm的四個點，測量時須將麥克風放置耳朵高度並朝上(麥克風上會有一張小貼紙，請將那面朝前)
- 如測量中遇到問題或找不到機器，請嘗試重新安裝電腦ARC程式，或是將擴大機回復原廠設定後斷電重插。

參考影片

- <https://youtu.be/VAIWvqVxmh4>
- <https://youtu.be/mmUmFHoSTsA>